

Docklight V1.9 User Manual 05/2009

Copyright 2009 Flachmann und Heggelbacher

Table of Contents

1 Copyright	1
2 Introduction	2
2.1 Docklight - Overview	2
2.2 Typical Applications	2
2.3 System Requirements	3
3 User Interface	5
3.1 Main Window	5
3.2 Clipboard - Cut, Copy & Paste	5
3.3 Notepad	6
4 Features and Functions	7
4.1 How Serial Data Is Processed and Displayed	7
4.2 Editing and Managing Sequences	7
5 Working with Docklight	8
5.1 Testing a Serial Device or a Protocol Implementation	8
5.2 Simulating a Serial Device	9
5.3 Monitoring Serial Communications Between Two Devices	11
5.4 Catching a Specific Sequence and Taking a Snapshot of the Communication	12
5.5 Logging and Analyzing a Test	13
5.6 Checking for Sequences With Random Characters (Receive Sequence Wildcards)	13
5.7 Saving and Loading Your Project Data	15
6 Working with Docklight (Advanced Features)	16
6.1 Sending Commands With Parameters (Send Sequence Wildcards)	16
6.2 How to Increase the Processing Speed and Avoid "Input Buffer Overflow" Messages	17
6.3 How to Obtain Best Timing Accuracy	18
7 Examples and Tutorials	19
7.1 Testing a Modem - Sample Project: ModemDiagnostics.ptp	19
7.2 Reacting to a Receive Sequence - Sample Project: PingPong.ptp	20
8 Reference	22
8.1 Menu and Toolbar	22
8.2 Dialog: Edit Send Sequence	23
8.3 Dialog: Edit Receive Sequence	24
8.4 Dialog: Create Log File(s)	25

8.5	Dialog: Find Sequence	25
8.6	Dialog: Send Sequence Parameter	26
8.7	Dialog: Project Settings - Communication	26
8.8	Dialog: Project Settings - Flow Control	27
8.9	Dialog: Project Settings - Communication Filter	28
8.10	Dialog: Options	28
8.11	Dialog: Customize HTML Output	29
8.12	Dialog: Expert Options	30
8.13	Keyboard Console	31
9	Support	33
9.1	Web Support and Troubleshooting	33
9.2	E-Mail Support	33
10	Appendix	34
10.1	ASCII Character Set Tables	34
10.2	Hot Keys	36
10.3	RS232 Connectors / Pinout	37
10.4	Standard RS232 Cables	39
10.5	Docklight Monitoring Cable RS232 SUB D9	41
10.6	Docklight Tap	41
11	Glossary / Terms Used	43
11.1	Action	43
11.2	Break	43
11.3	CAN	43
11.4	Character	43
11.5	CRC	43
11.6	DCE	44
11.7	DTE	44
11.8	Flow Control	44
11.9	LIN	44
11.10	MODBUS	44
11.11	Receive Sequence	45
11.12	RS232	45
11.13	RS422	45
11.14	RS485	46
11.15	Send Sequence	46
11.16	Sequence	46
11.17	Sequence Index	46
11.18	Serial Device Server	47
11.19	Snapshot	47
11.20	Trigger	47

11.21	UART	47
11.22	Virtual Null Modem	47
11.23	Wildcard	48

1 Copyright

Copyright 2009 Flachmann und Heggelbacher

All rights reserved. No parts of this work may be reproduced in any form or by any means - graphic, electronic, or mechanical, including photocopying, recording, taping, or information storage and retrieval systems - without the written permission of the publisher.

Trademarks

Products that are referred to in this document may be either trademarks and/or registered trademarks of the respective owners. The publisher and the author make no claim to these trademarks.

Microsoft and *Windows* are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Disclaimer

While every precaution has been taken in the preparation of this document, the publisher and the author assume no responsibility for errors or omissions, or for damages resulting from the use of information contained in this document or from the use of programs and source code that may accompany it. In no event shall the publisher and the author be liable for any loss of profit or any other commercial damage caused or alleged to have been caused directly or indirectly by this document.

Contact

E-Mail Support: docklight@fuh-edv.de

Flachmann und Heggelbacher
Waldkirchbogen 29
D-82061 Neuried
Germany
<http://www.fuh-edv.de>

2 Introduction

2.1 Docklight - Overview

Docklight is a testing, analysis and simulation tool for serial communication protocols (RS232, RS485/422 and others). It allows you to monitor communications between two serial devices or to test the serial communication of a single device. Docklight is easy to use and works on almost any standard PC running *Windows Vista*, *Windows XP*, *Windows 2000* or *Windows NT*.

Docklight's key functions include

- **simulating serial protocols** - Docklight can send out user-defined sequences according to the protocol used and it can react to incoming sequences. This makes it possible to simulate the behavior of a serial communication device, which is particularly useful for generating test conditions that are hard to reproduce with the original device (e.g. problem conditions).
- **logging RS232 data** - All serial communication data can be logged using two different file formats. Use plain text format for fast logging and storing huge amounts of data. An HTML file format, with styled text, lets you easily distinguish between incoming and outgoing data or additional information. Docklight can also log any binary data stream including ASCII 0 <NUL> bytes and other control characters.
- **detecting specific data sequences** - In many test cases you will need to check for a specific sequence within the RS232 data that indicates a problem condition. Docklight manages a list of such data sequences for you and is able to perform user-defined actions after detecting a sequence, e.g. taking a snapshot of all communication data before and after the error message was received.
- **responding to incoming data** - Docklight lets you specify user-defined answers to the different communication sequences received. This allows you to build a basic simulator for your serial device within a few minutes. It can also help you to trace a certain error by sending out a diagnostics command after receiving the error message.

Docklight will work with the COM communication ports provided by your operating system. Physically, these ports will be [RS232](#) SUB D9 interfaces in many cases. However, it is also possible to use Docklight for other communication standards such as [RS485](#) and [RS422](#), which have a different electrical design to RS232 but follow the RS232 communication mechanism. Docklight has also been successfully tested with many popular USB-to-Serial converters, [virtual null modem](#) software drivers, or Embedded Development tools that appear as a virtual COM port in Windows.

For RS232 full-duplex monitoring applications, we recommend our [Docklight Tap](#) USB accessory, or our [Docklight Monitoring Cable](#).


This manual only refers to RS232 serial connections in detail, since this is the basis for other serial connections mentioned above.

TIP: For getting started, have a look at the Docklight [sample projects](#), which demonstrate some of the basic Docklight functions.

2.2 Typical Applications


Docklight is the ideal tool to support your development and testing process for serial communication devices. Docklight may be used to

- [Test the functionality or the protocol implementation of a serial device.](#)
You may define control sequences recognized by your device, send them, log and analyze the responses and test the device reaction.




- [Simulate a serial device.](#)

Although rare, the possibility of a hardware fault must be considered in most systems. Imagine you have a device that sends an error message in the case of a hardware fault. A second device should receive this error message and perform some kind of reaction. Using Docklight you can easily simulate the error message to be sent and test the second device's reaction.



- [Monitor the communication between two devices.](#)

Insert Docklight into the communication link between two serial devices. Monitor and log the serial communication in both directions. Detect faulty communication sequences or special error conditions within the monitored communication. Take a snapshot of the communication when such an error condition has occurred.



2.3 System Requirements

Operating system

- Windows Vista, Windows XP, Windows 2000 or Windows NT

Hardware requirements


- Pentium processor 400 MHz or faster
- Minimum 64 MB RAM
- Minimum one COM port available. Two COM ports for monitoring communication between two serial devices.
- For low-latency monitoring using [Docklight Tap](#): One USB port

Additional cables or drivers may be required for connecting the equipment to be tested. See the sections on [Docklight Tap](#), [Docklight Monitoring Cable RS232 SUB D9](#), [Standard RS232 Cables](#) and [virtual null modem drivers](#).

3 User Interface

3.1 Main Window

The main window of Docklight is divided into four sections:



1. Toolbar and Status

All main Docklight functions may be selected from the [Toolbar](#). Additional information about the communication status and the current settings is shown in the status line below it.

2. Send Sequences

Define, edit and manage your [Send Sequences](#) here. Using the arrow symbol, the selected sequence can be sent out immediately. Double click on the blank field at the end of a list to create a new sequence. The sequence list can be reordered by dragging a sequence to a new position with the left mouse button pressed. A context menu (right mouse button) is available to cut, copy or paste entire Send Sequences to/from the [Clipboard](#). See [Editing and Managing Sequences](#) and [Dialog: Edit Send Sequence](#) for more information.

3. Receive Sequences

Define, edit and manage your [Receive Sequences](#) here. Double click on the blank field at the end of a list to create a new sequence. The Receive Sequence list supports the same reordering and clipboard operations as the Send Sequence list. You can also copy a Send Sequence to the clipboard and paste it into the Receive Sequence list. See [Editing and Managing Sequences](#) and [Dialog: Edit Receive Sequence](#) for more information.

4. Communication Window

Displays the outgoing and incoming communication on the serial port. Various display options are available for communication data, including ASCII / HEX / Decimal / Binary display, time stamps and highlighting (see [Options](#)). If serial communication is stopped, all data from the communications window may be copied to the clipboard or printed. You may also search for specific sequences using the [Find Sequence](#) function. See [How Serial Data is Processed and Displayed](#) for more information.

3.2 Clipboard - Cut, Copy & Paste

Docklight supports the *Windows* clipboard and its Cut, Copy and Paste operations. Clipboard operations are available in the

- Main Window - Send Sequences
- Main Window - Receive Sequences
- Main Window - Communication
- Main Window - Script Editor (Docklight Scripting only)
- [Dialog: Edit Send Sequence](#)

- [Dialog: Edit Receive Sequence](#)
- [Dialog: Find Sequence](#)
- [Dialog: Send Sequence Parameter](#)
- [Notepad](#)
- [Keyboard Console](#)

You can cut a serial data sequence from the communication window and create a new Send or Receive Sequence by simply pasting it into the appropriate list. Or edit a Send Sequence, copy a part of this sequence to the clipboard and create a new Receive Sequence out of it by pasting it into the Receive Sequence window.

TIP: Try the **right mouse button** to display a context menu for Cut, Copy and Paste operations.

3.3 Notepad

The Docklight Notepad is a separate window for writing down additional notes concerning your Docklight project (how to use the Send / Receive Sequences, notes on additional test equipment, etc.). The notepad window can be shown using the **F12** key or the menu **Tools > Show Notepad**. The notepad is a simple text box that does not offer formatting menus or toolbars, but you can paste formatted text from the *Windows*[clipboard](#).

The notepad contents are stored along with all other Docklight project settings (see [saving and loading your project data](#)). When opening a Docklight project file, the notepad is displayed automatically, if project notes are available.

NOTE: Closing the notepad window does not delete your notes. They will be still available when you press **F12** again. To remove all notes, empty the text box using **Ctrl+A** (Select All) and the **DEL** key.

4 Features and Functions

4.1 How Serial Data Is Processed and Displayed

Docklight handles all serial data in an 8 bit-oriented way. Every [sequence](#) of serial data consists of one or more 8 bit [characters](#). Docklight allows you to

- display the serial data in either ASCII, HEX, Decimal or Binary format
- copy serial data to the [clipboard](#) and paste it into a standard text file or a formatted *Microsoft® Word* document, or create a Send / Receive Sequence using the data.
- print out serial data, user comments and other information

Docklight's communication window shows the current communication on the selected serial port (s). Docklight distinguishes between two communication channels (channel 1 and channel 2), which represent the incoming and outgoing data in [Send/Receive Mode](#) or the two communication channels being observed in [Monitoring Mode](#). Channel 1 and channel 2 data are displayed using different colors or fonts, and the communication data may be printed or stored as a log file in plain text or HTML format.

Besides the serial data, Docklight inserts date/time stamps into the communication display. By default, a date/time stamp is inserted every time the data flow direction switches between channel 1 and channel 2, or before a new [Send Sequence](#) is transmitted. There are several options available for inserting additional time stamps. This is especially useful when monitoring a half-duplex line with only one communication channel. See [Options --> Date/Time Stamps](#)

Docklight is able to process serial data streams containing any ASCII code 0 - 255 decimal. Since there are non-printing control characters (ASCII code < 32) and different encodings for ASCII code > 127, not all of these characters can be displayed in the ASCII text window. Nonetheless, all characters will be processed properly by Docklight and can be displayed in HEX, Decimal or Binary format. Docklight will process the serial data on any language version of the *Windows* operating system in the same way, although the ASCII display might be different. For control characters (ASCII code < 32), an additional display option is available to display their text equivalent in the communication window. See [Options](#) dialog and Appendix, [ASCII Character Set Tables](#).

Docklight allows you to suppress all original serial data, if you are running a test where you do not need to see the actual data, but only the additional evaluations generated using [Receive Sequences](#). See the Project Settings for [Communication Filter](#).

4.2 Editing and Managing Sequences

A Docklight project mainly consists of user-defined sequences. These may be either [Send Sequences](#), which may be transmitted by Docklight itself, or [Receive Sequences](#), which are used to detect a special message within the incoming serial data.


Sequences are defined using the [Edit Send Sequence](#) or [Edit Receive Sequence](#) dialog window. This dialog window is opened

1. by choosing **Edit** from the context menu available using the **right mouse button**.
2. by double-clicking on an existing sequence or pressing **Ctrl + E** with the Send Sequence or Receive Sequence list selected.
3. when creating a new sequence by double-clicking on the blank field at the end of a list (or pressing **Ctrl + E**).
4. when pasting a new sequence into the sequence list.

Docklight supports the use of [wildcards](#) (e.g. wildcard "?" as a placeholder for one arbitrary character) within Receive Sequences and Send Sequences. See the sections [sending commands with parameters](#) and [checking for sequences with random characters](#) for details and examples.

5 Working with Docklight

5.1 Testing a Serial Device or a Protocol Implementation



Preconditions


- You need the specification of the protocol to test, e.g. in written form.
- The serial device to test should be connected to one of the PC's COM ports. See section [Standard RS232 Cables](#) for details on how to connect two serial devices.
- The serial device must be ready to operate.

Performing the test

A) Creating a new project

Create a new Docklight project by selecting the menu **File >  New Project**

B) Setting the Communication Options

1. Choose the menu **Tools >  Project Settings...**
2. Choose communication mode **Send/Receive**
3. At **Send/Receive on comm. channel**, set the COM Port where your serial device is connected.
4. Set the baud rate and all other **COM Port Settings** required.
5. Confirm the settings and close the dialog by clicking the **OK** button.

C) Defining the Send Sequences to be used

You will probably test your serial device by sending specific sequences, according to the protocol used by the device, and observe the device's reaction. Perform the following steps to create your list of sequences:

1. Double click on the last line of the [Send Sequences](#) table. The [Edit Send Sequence](#) dialog is displayed (see also [Editing and Managing Sequences](#)).
2. Enter a **Name** for the sequence. The sequence name should be unique for every Send Sequence defined.
3. Enter the **Sequence** itself. You may enter the sequence either in ASCII, HEX, Decimal or Binary format. Switching between the different formats is possible at any time using the **Edit Mode** radio buttons.
4. After clicking the **OK** button the new sequence will be added to the Send Sequence lists.

Repeat steps 1 - 4 to define the other Send Sequences needed to perform your test.


D) Defining the Receive Sequences used

If you want Docklight to react when receiving specific sequences, you have to define a list of Receive Sequences.

1. Double click on the last line of the [Receive Sequences](#) table. The dialog [Edit Receive Sequence](#) is displayed. The dialog consist of three parts: **Name** field, **Sequence** field, and **Action** field.
2. Edit the **Name** and **Sequence** fields.
3. Specify an [Action](#) to perform after the sequence has been received by Docklight. There are four types of actions available:
 - Answer** - After receiving the sequence, transmit one of the Send Sequences.
 - Comment** - After receiving the sequence, insert a user-defined comment into the communication window (and log file, if available).
 - Trigger** - This is an advanced feature described in [Catching a specific sequence...](#)
 - Stop** - After receiving the sequence, Docklight stops communications.
4. Click the **OK** button to add the new sequence to the list.


Repeat steps 1 - 4 to define the other Receive Sequences you need to perform your test.

E) Storing the project

Before running the actual test, it is recommended that the communication settings and sequences defined be stored. This is done using the menu **File >  Save Project**.


F) Running the test

Start Docklight by choosing **Run >  Start Communication**.

Docklight will open a serial connection according to the parameters specified. It will then display all incoming and outgoing communication in the communication window. Use the  **Send** button to send one of the defined sequences to the serial device. The on-screen display of all data transfer allows you to check the device's behavior. All protocol information can be logged in a text file for further analysis. Please see section [Logging and analyzing a test](#).

TIP: Using the [notepad window](#) (F12 key / menu **Tools > Show Notepad**), you can easily take additional notes, or copy & paste parts of the communication log for further documentation.

5.2 Simulating a Serial Device



Preconditions

- You need the specification of the behavior of the serial device you want to simulate, e.g. what kind of information is sent back after receiving a certain command.
- A second device is connected to a PC COM port, which will communicate with your simulator.

This second device and its behavior is the actual object of interest. An example could be a device that periodically checks the status of an UPS (Uninterruptible Power Supply) using a serial communication protocol. You could use Docklight to simulate basic UPS behavior and certain UPS problem cases. This is very useful when testing the other device, because it can be quite difficult to reproduce an alarm condition (like a bad battery) at the real UPS.

NOTE: The second device may also be a second software application. It is possible to run both Docklight and the software application on the same PC. Simply use a different COM port for each of the two applications and connect the two COM ports using a [RS232 null modem cable](#). You can also use a [virtual null modem](#) for this purpose.

Performing the test

A) Creating a new project

Create a new Docklight project by selecting the menu **File >  New Project**

B) Setting the Communication Options

1. Choose the menu **Tools >  Project Settings...**
2. Choose communication mode **Send/Receive**
3. At **Send/Receive on comm. channel**, set the COM Port where your serial device is connected.
4. Set the baud rate and all other **COM Port Settings** required.
5. Confirm the settings and close the dialog by clicking the **OK** button.

C) Defining the Send Sequences used

Define all the responses of your simulator. Think of responses when the simulated device is in normal conditions, as well as responses when in fault condition. In the UPS example mentioned above, a battery failure would be such a problem case that is hard to reproduce with the original equipment. To test how other equipment reacts to a battery failure, define the appropriate response sequence your UPS would send in this case.


NOTE: See [Testing a serial device...](#) to learn how to define Send Sequences.

D) Defining the Receive Sequences used

In most cases, your simulated device will not send unrequested data, but will be polled from the other device. The other device will use a set of predefined command sequences to request different types of information. Define the command sequences that must be interpreted by your simulator here.

For every command sequence defined, specify **Answer** as an action. Choose one of the sequences defined in C). If you want to use two or more alternative response sequences, make several copies of the same Receive Sequence, give them a different name (e.g. "status cmd - answer ok", "status cmd - answer battery failure", "status cmd - answer mains failure") and assign different Send Sequences as an action. In the example, you would have three elements in the Receive Sequences list that would respond to the same command with three different answers. During the test you may decide which answer should be sent by checking or unchecking the list elements using the **Active** column.

E) Storing the project

Before running the actual test, it is recommended that the communication settings and sequences defined be stored. This is done using the menu **File >  Save Project**.

F) Running the test


Start Docklight by choosing **Run >  Start Communication**.

Docklight will now respond to all commands received from the connected serial device.

The on-screen data transfer display allows you to monitor the communications flow. All protocol information can be logged to a text file for further analysis. See section [Logging and analyzing a test](#).

TIP: Using the [notepad window](#) (F12 key / menu **Tools > Show Notepad**), you can easily take additional notes, or copy & paste parts of the communication log for further documentation.

5.3 Monitoring Serial Communications Between Two Devices



Preconditions


- A [Docklight Monitoring Cable](#) or a [Docklight Tap](#) is required to tap the RS232 TX signals of both serial devices and feed them into Docklight, while not interfering with the communications between the devices.
- For a [Docklight Monitoring Cable](#) setup, two COM ports must be available on your PC for monitoring. Each port will receive the data from one of the serial devices being monitored.
- For a [Docklight Tap](#) setup, please make sure you have installed up-to-date USB drivers (FTDI drivers), as available on our [Docklight Download](#) page.
- Device 1 and Device 2 must be ready to operate.

Performing the test

A) Creating a new project

Create a new Docklight project by selecting the menu **File >  New Project**

B) Setting the Communication Options

1. Choose the menu **Tools >  Project Settings...**
2. Choose communication mode **Monitoring**

Alternative 1 - Using Docklight Monitoring Cable

3. At **Receive Channel 1**, set the COM Port where the monitoring signal from serial device 1 is received. At **Receive Channel 2**, set the COM port for the second device.

NOTE: In Docklight Monitoring Mode, all received data from one COM port is re-sent on the TX channel of the opposite COM port ("Data Forwarding"). This does not have any effect for [Docklight Monitoring Cable](#) setups, since the TX signal is not connected. But it can be useful for special applications where you need to route the serial data traffic through Docklight using standard RS232 cabling. If you require a pure passive monitoring behavior where no TX data appears, you can disable the "Data Forwarding" using the menu **Tools > [Expert Options...](#)**

Alternative 2 - Using Docklight Tap

3. At **Receive Channel 1**, open the dropdown list, scroll down to the **-- USB Taps --** section and choose the first Tap port, e.g. **TAP0**. At **Receive Channel 2**, the second tap port (e.g. **TAP1**) is selected automatically.

4. Set the baud rate and all other communication parameters for the protocol being used

NOTE: Make sure your PC's serial interfaces port works properly at the baud rate and for the communication settings used by Device 1 and Device 2. If Device 1 and 2 use a high speed data transfer protocol, the PC's serial interfaces and the Docklight software itself might be too slow to receive all data properly.


5. Confirm the settings and close the dialog by clicking the **OK** button.

C) Defining the Receive Sequences used



Define Receive Sequences, which should be marked in the test protocol or trigger an action within Docklight. Docklight checks for Receive Sequence on both monitoring channels, i.e. it does not matter whether the sequences come from serial device 1 or serial device 2.


NOTE: Since a special monitoring cable is used for this test, all communication between serial device 1 and serial device 2 will remain unbiased and no additional delays will be introduced by Docklight itself. This is particularly important when using Docklight for tracking down timing problems. This means, however, that there is no way to influence the serial communication between the two devices. While communication mode **Monitoring** is selected, it is not possible to use Send Sequences.

D) Storing the project

Before running the actual test, it is recommended to store the communication settings and sequences defined. This is done using the menu **File >  Save Project**.

E) Running the test

Start Docklight by choosing **Run >  Start Communication**, then activate the serial devices 1 and 2 and perform a test run. Docklight will display all communication between serial device 1 and serial device 2. Docklight uses different colors and font types to make it easy to distinguish between data transmitted by device 1 or device 2. The colors and font types can be chosen in the [Display](#) tab of the **Tools >  Options...** dialog.

TIP: The  [Snapshot Function](#) allows you to locate a rare sequence or error condition in a communication protocol with a large amount of data.

TIP: See the sections [How to Increase the Processing Speed...](#) and [How to Obtain Best Timing Accuracy](#) to learn how to adjust Docklight for applications with high amounts of data, or increased timing accuracy requirements.

5.4 Catching a Specific Sequence and Taking a Snapshot of the Communication

When [monitoring serial communications between two devices](#), you might want to test for a rare error and the interesting parts would be just the serial communication before and after this event. You could look for this situation by [logging the test](#) and searching the log files for the characteristic error sequence. This could mean storing and analyzing several MB of data when you are actually just looking for a few bytes though, if they appeared at all. As an alternative, you can use the [Snapshot](#) feature as described below.

Preconditions

- Docklight is ready to run a test as described in the previous use cases, e.g. [monitoring serial communications between two devices](#).


Taking a snapshot

- A) Defining a trigger for the snapshot

1. Define the sequence that appears in your error situation as a [Receive Sequence](#).
2. Check the **Trigger** tab in the "action" part of the Receive Sequence dialog: The trigger option must be enabled if this is the sequence that you want to track down.

NOTE: Do not forget to disable the trigger option for all other Receive Sequences that should be ignored in your test so that they do not trigger the snapshot.

B) Creating a snapshot

Click on the  **Snapshot** button of the toolbar. Docklight will start communications, but will not display anything in the communication window. If the trigger sequence is detected, Docklight will display communication data before and after the trigger event. Further data is processed, until the trigger sequence is located roughly in the middle of the communication window. Docklight will then stop communication and position the cursor at the trigger sequence.

5.5 Logging and Analyzing a Test

Preconditions

- Docklight is ready to run a test as described in the previous use cases, e.g. [Testing a serial device or a protocol implementation](#)


Logging the test

Click on the  **Start Logging** button on the main toolbar.

A dialog window will open for choosing [log file settings](#).

For each representation (ASCII, HEX, ...), a separate log file may be created. Choose at least one representation. Log files will have a ".txt" or ".htm" file extension. Docklight additionally adds the representation type to the file name to distinguish the different log files. E.g. if the user specifies "Test1" as the base log file name, the plain text ASCII file will be named "Test1_asc.txt", whereas an HTML HEX log file will be named "Test1_hex.htm".

Confirm your log file settings and start logging by clicking the **OK** button.

To stop logging and close the log file(s), click the  **Stop Logging** button on the main toolbar. Unless the log file(s) have been closed, it is not possible to view their entire contents.

5.6 Checking for Sequences With Random Characters (Receive Sequence Wildcards)

Many serial devices support a set of commands to transmit measurement data and other related information. In common text-based protocols the response from the serial device consists of a fixed part (e.g. "temperature="), and a variable part, which is the actual value (e.g. "65F"). To detect all these responses correctly in the serial data stream, you can define Receive Sequences containing [wildcards](#).

Take, for example, the following situation: A serial device measures the temperature and periodically sends the actual reading. Docklight shows the following output:

```
10/30/2008 10:20:08.022 [RX] - temperature=82F<CR>
10/30/2008 10:22:10.558 [RX] - temperature=85F<CR>
10/30/2008 10:24:12.087 [RX] - temperature=93F<CR>
10/30/2008 10:26:14.891 [RX] - temperature=102F<CR>
...
```

Defining an individual Receive Sequence for every temperature value possible would not be a practical option. Instead you would define one Receive Sequence using wildcards. For example:
 t | e | m | p | e | r | a | t | u | r | e | = | ? | # | # | F | r
 ("r" is the terminating <CR> Carriage Return character)

This ReceiveSequence would trigger on any of the temperature strings listed above. It allows a 1-3 digit value for the temperature (i.e. from "0" to "999"). The following step-by-step example describes how to define the above sequence. See also the [additional remarks](#) at the end of this section for some extra information on '#' wildcards.

Preconditions

- Docklight is ready to run a test as described in the previous use cases, e.g. [testing a serial device or a protocol implementation](#).
- The serial device (the temperature device in our example) is operating.

Using Receive Sequences with wildcards

A) Preparing the project

Create a new Docklight project and set up all communication parameters.

B) Defining the Receive Sequences used

1. [Create a new Receive Sequence](#). Enter a **Name** for the sequence.
2. Enter the fixed part of your expected answer in the **Sequence** section. For our example you would enter the following sequence in ASCII mode:
 t | e | m | p | e | r | a | t | u | r | e | = |
 t | e | m | p | e | r | a | t | u | r | e | = |
3. Open the popup / context menu using the **right mouse button**, and choose **Wildcard '?' (matches one character)** to insert the first wildcard at the cursor position. Add two '#' wildcards using the popup menu **Wildcard '#' (matches zero or one character)**. The sequence now looks like this:
 t | e | m | p | e | r | a | t | u | r | e | = | ? | # | #
4. Enter the fixed tail of our temperature string, which is a letter 'F' and the terminating <CR> character. You can use the default [control character shortcut Ctrl+Enter](#) to enter the <CR> / ASCII code 13. The sequence is now:
 t | e | m | p | e | r | a | t | u | r | e | = | ? | # | # | F | r
5. Specify an **Action** to perform after a temperature reading has been detected.
6. Click **OK** to add the new sequence to the Receive Sequence list.

NOTE: To distinguish the wildcards '?' and '#' from the regular question mark or number sign characters (decimal code 63 / 35), the wildcards are shown on a different background color within the sequence editor.

C) Running the test

Start Docklight by choosing **Run >  Start Communication**.

Docklight will now detect any temperature reading and perform the specified action.

Additional notes on '#' wildcards

1. The '#' wildcard enables the user to check for variable-length sequences. However, an algorithm checking for any possible matching character combination would need to perform an increasing number of sequence comparisons with every additional '#' wildcard. This becomes obvious if you replace the '#'-based sequence by an equivalent set of sequences that only contain '?' wildcards (matches exactly one character).

A check for "Hello#World#!" could be replaced by a check for

"HelloWorld!" plus
 "Hello?World!" plus
 "HelloWorld?!" plus
 "Hello?World?!"

As can be seen, every "#" wildcard doubles the number of comparison operations required. Therefore, Docklight performs a simplified '#' check. The Receive Sequence "Hello#World!" will work for

"HelloWorld!" or

"HelloXWorld!", but will not trigger on

"HelloWWorld!".

The reason for this is that since the first 'W' is considered a part of "World", Docklight forwards its internal search cursor by one. The next character expected is an 'o', but the data stream says 'W' again, so the comparison algorithm stops here.

Keep this limitation in mind when defining Receive Sequences with '#' wildcards. If you need a Receive Sequence that triggers on "HelloWWorld!" as well, define an additional Receive Sequence using the '?' wildcard character:

"Hello?World!"

2. '#' wildcards immediately before a '?' wildcard have no effect. The search cursor will always be forwarded to the '?' wildcard, since the '?' matches any arbitrary character. The receive sequence "Hello##?World" will behave like the receive sequence "Hello?World"

3. '#' wildcards at the beginning or at the end of an receive sequence have no effect. The receive sequence "###HelloWorld###" will behave like the receive sequence "HelloWorld".

5.7 Saving and Loading Your Project Data

All project data may be saved in a Docklight project file using the menu **File >  Save Project** or **File > Save Project As...**

The project data includes

- [Send Sequences](#) defined
- [Receive Sequences](#) defined
- additional [Project Settings](#): communication mode, COM ports used, COM port settings (baud rate, parity, ...)
- the [Notepad](#) contents

It is recommended to save your current project before starting a test run. Please note the difference between storing the project settings as described here and logging the communication during a test (see section [logging and analyzing a test](#)). Test run results are stored separately from Projects.

Loading a project is done using the **File >  Open Project...** menu.

6 Working with Docklight (Advanced Features)

6.1 Sending Commands With Parameters (Send Sequence Wildcards)

When testing a serial device, the device will most likely support a number of commands that include a parameter.

Example: A digital camera supports a command to set the exposure time. For setting the exposure time to 25 milliseconds, you need to send the following sequence:

e | x | p | | 0 | 2 | 5 | r ("r" is a terminating <CR> Carriage Return character)

To avoid defining a new Send Sequence for every exposure time you want to try, you can use a Send Sequence with [wildcards](#) instead:

e | x | p | | ? | ? | ? | r

The following step-by-step example describes how to define an exposure time command with a parameter and use a different exposure value each time the sequence is sent.

Preconditions

- Docklight is ready to run a test as described in [testing a serial device or a protocol implementation](#).

Performing the test using commands with parameters

A) Preparing the project

Create a new Docklight project and set up all communication parameters.


B) Defining the commands used

1. [Create a new Send Sequence](#). Enter a **Name** for the sequence.
2. Enter the fixed part of your command in the **Sequence** section. For our example you would enter the following sequence in ASCII mode:
e | x | p | |
3. Now open the context menu using the **right mouse button**, and choose **Wildcard '?' (matches one character)** to insert one wildcard at the cursor position. In our example we would have to repeat this until there are three '?' wildcards for our three-digit exposure time. The sequence now looks like this:
e | x | p | | ? | ? | ?
4. Now add the terminating <CR> character, using the default [control character shortcut Ctrl +Enter](#). The example sequence now is
e | x | p | | ? | ? | ? | r
5. Click **OK** to add the new sequence to the Send Sequence list.

Repeat steps 1 - 5 to define other commands needed to perform your test.

NOTE: To distinguish a '?' wildcard from a question mark ASCII character (decimal code 63), the wildcard is shown on a different background color within the sequence editor.

C) Sending a command to the serial device

1. Use the  **Send** button to open the serial communication port and send one command to the serial device.
2. The communication pauses and the [Send Sequence Parameter](#) dialog pops up, allowing you to enter the parameter value. In our example, an exposure time, e.g. "025".
3. Confirm by pressing **Enter**. The sequence is now sent to the serial device.

It is possible to define commands with several parameters, using several wildcard areas within one sequence. The [Send Sequence Parameter](#) dialog will then appear several times before sending out a sequence.

NOTE: If you are using **Wildcard '?'**, you must provide exactly one character for each '?' when sending the sequence. For variable-length parameters use **Wildcard '#' (matches zero or one character)**.

NOTE: You cannot use a Send Sequence with wildcards as an automatic answer for a Receive Sequence (see [Action](#)).


6.2 How to Increase the Processing Speed and Avoid "Input Buffer Overflow" Messages

When [monitoring serial communications between two devices](#), Docklight cannot control the amount of incoming data. Since Docklight applies a number of formatting and conversion rules on the serial data, only a limited number of bytes per seconds can be processed. There are numerous factors that determine the processing speed, e.g. the PC and COM devices used, the [Display Settings](#), and the [Receive Sequence Actions](#) defined. It is therefore not possible to specify any typical data rates.



If Docklight cannot keep up with the incoming data, it adds the following comment to the communication data display:

`DOCKLIGHT reports: Input buffer overflow on COM1`

TIP: Search for this message using the  **Find Sequence in Communication Window...** (Ctrl + F) function.

Docklight will also react slowly to any user input, including a  **Stop communication** command.

If you are experiencing the above behavior, Docklight offers you several ways to increase the data throughput.

1. Simplify the display output:
 - Deactivate all unneeded [Display Modes](#) in the  **Options...** dialog
 - Use [Plain Text Mode](#) instead of "Formatted Text Output"
 - If you are using ASCII mode, disable the [Control Characters Description](#) option
2. Log the communication data to a plain text file instead of using the communication window(s):
 - Use the "plain text" [Log File Format](#)
 - Create only a log file for the [Representation](#) (ASCII / HEX / Decimal / Binary) you actually need
 - Disable the communication windows while logging, using the [High Speed Logging](#) option
3. Use the [Communication Filter](#) from the  **Project Settings...** dialog, and disable the original serial data for one or both communication directions. This is especially useful if you actually know what you are looking for and can define one or several [Receive Sequences](#) for this pieces of data. These Receive Sequences can print a comment each time the sequence appears in the data stream so you still know what has happened, even if the original serial data is not displayed by Docklight.

6.3 How to Obtain Best Timing Accuracy

Many RS232 monitoring applications – including Docklight – can only provide limited accuracy when it comes to time tagging the serial data. As a result, data from the two different communication directions can be displayed in chronologically incorrect order, or several telegrams from one communication direction can appear as one chunk of data.

This behavior is not caused by poor programming, but is rather characteristic for a PC/Windows system, and the various hardware and software layers involved. Unspecified delays and timing inaccuracies can be introduced by:

- The COM device's chipset, e.g. the internal FIFO (First-In-First-Out) data buffer.
- The USB bus transfer (for USB to Serial converters).
- The serial device driver for Windows.
- The task/process scheduling in a multitasking operating system like Windows.
- The accuracy of the date/time provider.

Docklight comes with a very accurate date/time provider with milliseconds granularity, but it still needs to accept the restrictions from the hardware and software environment around it.

Here is what you can do to minimize additional delays and inaccuracies and achieve a typical time tagging accuracy of 5 milliseconds or better:

1. Get our [Docklight Tap](#) for lowest USB-related latency times. Or use on-board RS232 ports, if still available on your PC.
2. Choose [External / High Priority Process Mode](#) in the **Tools > Expert Options...** dialog.
3. When monitoring high amounts of data, use the recommendations from the previous section [How to Increase the Processing Speed...](#) to avoid input buffer overflows and that the computer become irresponsive because of high CPU usage.

NOTE: The **Expert Options...** recommended above will change the overall system balance and must be used with care. Best results can be achieved only when logged in as an Administrator. Please make sure you understood the remarks and warning in the [documentation](#).

7 Examples and Tutorials

This chapter describes two sample projects that demonstrate some of Docklight's basic functions. The corresponding Docklight project files (.ptp files) can be found in the **\Samples** folder within the Docklight installation directory (e.g. **C:\Program Files\FuH\Docklight V1.9\Samples**).

NOTE: If you are logged on with a restricted user account, you will not have permission to make any changes in the program files directory. In this case, saving a project file or any other data into the **\Samples** folder will produce an error.

NOTE: For additional sample projects and Application Notes, see our online resources at www.docklight.de/examples_en.htm




7.1 Testing a Modem - Sample Project: ModemDiagnostics.ptp

The Docklight project **ModemDiagnostics.ptp** can be used to perform a modem check. A set of modem diagnostic commands are defined in the Send Sequences list.

This is a simple example for [Testing a serial device or a protocol implementation](#). The sample project uses the [communication settings](#) listed below. This should work for most standard modems.

Communication Mode	Send/Receive
COM Port Settings	9600 Baud, No parity, 8 Data Bits, 1 Stop Bit

Getting started

- Connect the modem to an available COM port, e.g. COM1, and switch it on. The demo may also run on a notebook with a built-in modem. In many cases you will find your notebook's built-in modem on COM3, so you can try and run the demo without modifying the project settings.
- Go to the  **Project Settings...** dialog and make sure you have selected the same COM Port for **Send/Receive on comm. channel**.
- Press the  **Start Communication** button in the toolbar.
- Try sending any of the predefined modem commands by pressing the  **Send** button

You should now receive a response from your modem, e.g. "OK" if your command was accepted, a model identification number, etc. The response will vary with the modem model.

After sending several sequences, the Docklight communication window could look like this:

```
3/8/2009 15:00:44.034 [TX] - ATQ0V1E0<CR><LF>
3/8/2009 15:00:44.040 [RX] - <CR><LF>
OK<CR><LF>

3/8/2009 15:00:44.608 [TX] - AT+GMM<CR><LF>
3/8/2009 15:00:44.610 [RX] - <CR><LF>
H.324 video-ready rev. 1.0<CR><LF>
<CR><LF>
OK<CR><LF>

3/8/2009 15:00:45.049 [TX] - AT+FCLASS=?<CR><LF>
3/8/2009 15:00:45.060 [RX] - <CR><LF>
0,1,8<CR><LF>
```


...

Further Information

The Send Sequences list includes the following standard AT modem commands:



Send Sequence	Description / Modem Response
ATQ0V1E0	Initializes the query.
AT+GMM	Model identification (ITU V.250 recommendation is not supported by all modems).
AT+FCLASS=?	Fax classes supported by the modem, if any.
AT#CLS=?	Shows whether the modem supports the Rockwell voice command set.
ATI<n>	Displays manufacturer's information for <n> = 1 through 7. This provides information such as the port speed, the result of a checksum test, and the model information. Check the manufacturer's documentation for the expected results.

The **\Samples** folder also contains a log file **ModemDiagnostics_Logfile_asc.txt**. It shows a test run where the above Send Sequences were sent to a real modem.

7.2 Reacting to a Receive Sequence - Sample Project: PingPong.ptp

The Docklight project **PingPong.ptp** is a simple example for how to define and use Receive Sequences.

Getting started

- Go to the  **Project Settings...** dialog and choose a COM port.
- Apply a simple loopback to this COM port: Connect Pin 2 (RX) with Pin 3 (TX). See [RS232 SUB D9 Pinout](#).
- Now press the  **Send** button for either of the two Send Sequences. Communication is started and the Send Sequence is transmitted. It will of course be instantly received on the COM port's RX line.

Docklight will detect the incoming data as being one of the defined [Receive Sequences](#). It will then perform the action predefined for this event, which is sending out another sequence. As a result, Docklight will send out alternating Send Sequences - "Ping" and "Pong".

- Use the  **Stop communication** button to end the demo.

The Docklight communication display should look similar to this:

```

3/8/2009 16:25:44.201 [TX] - ----o Ping
3/8/2009 16:25:44.216 [RX] - ----o Ping "Ping" received
3/8/2009 16:25:44.218 [TX] - o---- Pong
3/8/2009 16:25:44.233 [RX] - o---- Pong "Pong" received
3/8/2009 16:25:44.236 [TX] - ----o Ping
3/8/2009 16:25:44.251 [RX] - ----o Ping "Ping" received
3/8/2009 16:25:44.254 [TX] - o---- Pong
3/8/2009 16:25:44.268 [RX] - o---- Pong "Pong" received
3/8/2009 16:25:44.271 [TX] - ----o Ping
3/8/2009 16:25:44.286 [RX] - ----o Ping "Ping" received
3/8/2009 16:25:44.289 [TX] - o---- Pong
3/8/2009 16:25:44.303 [RX] - o---- Pong "Pong" received
3/8/2009 16:25:44.307 [TX] - ----o Ping

```



```
3/8/2009 16:25:44.322 [RX] - ----o Ping "Ping" received
3/8/2009 16:25:44.324 [TX] - o---- Pong
...
```

See also the corresponding log files in the \Samples folder (**PingPong_Logfile_asc.htm** and **PingPong_Logfile_hex.htm**).

Further Information

This demo project can also be run in three alternative configurations:

1. Run two Docklight applications on the same PC using different COM ports. The two COM ports are connected using a [simple null modem cable](#).
2. Instead of two RS232 COM ports and a null modem cable you can use a [virtual null modem](#).
3. Use two PCs and run Docklight on each PC. Connect the two PCs using a simple null modem cable.

8 Reference

8.1 Menu and Toolbar

File Menu

**New Project**

Close the current Docklight project and create a new one.

**Open Project ...**

Close the current Docklight project and open another project.

Import Sequence List ...

Import all [Send Sequences](#) and [Receive Sequences](#) from a second Docklight project.

**Save Project / Save Project As ...**

Save the current Docklight project.

Print Project ...

Print the project data, i.e. the list of defined Send Sequences and Receive Sequences. The sequences are printed in the same representation (ASCII, HEX, Decimal or Binary) that is used in the Docklight main window. The representation may be chosen using the [Options](#) dialog window.

**Print Communication ...**

Print the contents of the communication window. The communication data is printed in the same representation that is currently visible in the communication window.

Exit

Quit Docklight.

Edit Menu

Edit Send Sequence List ...

Edit the [Send Sequences](#) list, i.e. add new sequences or delete existing ones.

Edit Receive Sequence List ...

Edit the [Receive Sequences](#) list, i.e. add new sequences or delete existing ones.

Swap Send and Receive Sequence Lists

Convert all Send Sequences into Receive Sequences and vice versa.

**Find Sequence in Communication Window...**

Find a specific sequence within the data displayed in the communication window. See the [Find Sequence](#) function.

**Clear Communication Window**

Delete the contents of the communications window. This applies to all four representations (ASCII, HEX, Decimal, Binary) of the communication window.

Run Menu

**Start communication**

Open the communication ports and enable serial data transfer.

**Stop communication**

Stop serial data transfer and close the communication ports.

Tools Menu



Start Communication Logging ...

Create new log file(s) and start logging the incoming/outgoing serial data. See [logging and analyzing a test](#).



Stop Communication Logging

Stop logging and close the currently open log file(s).



Start Snapshot Mode

Wait for a trigger sequence and take a snapshot. See [Catching a specific sequence...](#)



Stop Snapshot Mode

Abort a snapshot and reenale the communication window display.



Keyboard Console On

Enable the [keyboard console](#) to send keyboard input directly.



Keyboard Console Off

Disable the keyboard console.

Show Notepad

Show the [notepad window](#).



Project Settings...

Select the current project settings ([communication settings](#), [flow control settings](#), [communication filter...](#)).



Options...

Select [general settings](#) (e.g. display).

Expert Options...

Select [expert program options](#) intended for advanced users and specific applications (e.g. high monitoring accuracy).

8.2 Dialog: Edit Send Sequence

This dialog is used to define new [Send Sequences](#) and edit existing ones (See also [Editing and Managing Sequences](#)).

Index

The index of the sequence displayed below. The first sequence has index 0 (zero).

1 - Name

Unique name for this sequence (e.g. "Set modem speaker volume"). This name is for referencing the sequence. It is not the data that will be sent out through the serial port. See "2 - Sequence" below.

2 - Sequence

The [character sequence](#) that will be transmitted through the serial port.

3 - Additional Settings

Check the "Send periodically..." option to define a sequence that is sent periodically. A time interval between 0.01 seconds and 9999 seconds can be specified.

NOTE: The *Windows* reference time used for this purpose has only limited precision. Time intervals < 0.03 seconds will usually not be accurate.

Wildcards

[Wildcards](#) can be used to introduce parameters into a Send Sequence that you wish to insert manually each time the sequence is sent. See section [Sending commands with parameters](#) for details and examples.

Control Character Shortcuts

Using keyboard shortcuts is a great help when editing a sequence that contains both printing characters (letters A-z, digits 0-9, ...) and non-printing control characters (ASCII code 0 to 31). Predefined shortcuts are:

Ctrl+Enter for carriage return / <CR> / decimal code 13

Ctrl+Shift+Enter for line feed / <LF> / decimal code 10

Use  [Options... --> Control Character Shortcuts](#) to define other shortcuts you find useful.

8.3 Dialog: Edit Receive Sequence

This dialog is used to define new [Receive Sequences](#) and edit existing ones (See also [Editing and Managing Sequences](#)).

Index

The index of the sequence displayed below. The first sequence has index 0 (zero).

1 - Name

Unique name for this sequence (e.g. "Ping received"). This name is for referencing the sequence. It is not the sequence received through the serial port. See "2 - Sequence" below.

2 - Sequence

The [character sequence](#) which should be detected by Docklight within the incoming serial data.

3 - Action

The action(s) performed when Docklight detects the sequence defined above.

You may choose from the following actions:

- **Answer** - After receiving the sequence, transmit one of the [Send Sequences](#). Only Send Sequences that do not contain [wildcards](#) can be used as an automatic answer.
- **Comment** - After receiving the sequence, insert a user-defined comment into the communication window (and log file, if available).
- **Trigger** - Trigger a snapshot when the sequence is detected. This is an advanced feature described in the section [Catching a specific sequence...](#)
- **Stop** - Stop communications and end the test run.

Wildcards

[Wildcards](#) can be used to test for sequences that have a variable part with changing values (e.g. measurement or status values). See section [Checking for sequences with random characters](#) for details and examples.

Control Character Shortcuts

Using keyboard shortcuts is a great help when editing a sequence that contains both printing characters (letters A-z, digits 0-9, ...) and non-printing control characters (ASCII code 0 to 31). Predefined shortcuts are:

Ctrl+Enter for carriage return / <CR> / decimal code 13

Ctrl+Shift+Enter for line feed / <LF> / decimal code 10

Use  [Options... --> Control Character Shortcuts](#) to define other shortcuts you find useful.

8.4 Dialog: Create Log File(s)

Menu Tools >  Start Communication Logging ...

Log file format

The available log formats are plain text (.txt) files or HTML files for web browsers (.htm). Plain text files are a good choice if you expect your log files to become very large. HTML log files are more comfortable to analyze, because they include all the visual formatting of the communication windows (colors, bold characters, italic characters). However, the file will be larger than a plain text file and some browsers may process large HTML files quite slowly. If you have specific requirements on the output format, you can [customize the HTML output](#).

Log file directory and base name

Choose the directory and base file name for the log file(s) here. The actual file path used for the individual log file representations are displayed in the text boxes within the "Log file representation" frame.

Overwrite / append mode

Choose "append new data" if you do not want Docklight to overwrite existing log file(s). Docklight will then insert a "start logging / stop logging" message when opening / closing the log files. This is so that when in 'append mode' it is still possible to see when an individual log file session started or ended.

Representation

A separate log file may be created for each data representation (ASCII, HEX, ...). Choose at least one representation. The log files will have a ".txt" or ".htm" file extension. Docklight additionally adds the representation type to the file name to distinguish the different log files. E.g. if the user specifies "Test1" as the base log file name, the plain text ASCII log file will be named "Test1_asc.txt", whereas the plain text HEX log file will be named "Test1_hex.txt".

High speed logging

If you are monitoring a high speed communication link or if you are running Docklight on a slow computer, Docklight may not be able to catch all the transmitted data or may even freeze (no response to any user input). In this case, try disabling the communication window output while logging the data to a file. Docklight will run much faster, since the display formatting uses considerable CPU time.

8.5 Dialog: Find Sequence

Menu Edit >  Find Sequence in Communication Window...

The **Find Sequence** function searches the contents of the communication window. The search is performed in the communication window tab that is currently selected (ASCII, HEX, Decimal or Binary). You may, however, define your search string in any other representation.

Searching the communication windows is only possible if the communication is stopped.

You can search for anything that is already defined as a [Send Sequence](#) or a [Receive Sequence](#), or you may define a custom search sequence.

NOTE: If you are looking for a sequence within the ASCII communication window, please remember the following limitations:

- The **Find Sequence** function is not able to locate sequences containing non-printing control characters (ASCII decimal code < 32) or other special characters (decimal code > 127). This is due to the nature of the ASCII display. Search using the HEX or Decimal communication window tab instead.
- In ASCII mode, the **Find Sequence** function will treat date/time stamps and any other comments in the same way as regular communication data. In HEX / Decimal / Binary mode, all

additional information is ignored as long as it does not look like a character byte value.

8.6 Dialog: Send Sequence Parameter

Type in one or several value(s) for a [Send Sequence with wildcards](#) here. As with the Edit Send/Receive Sequence dialog, you may use [control character shortcuts](#) or [clipboard functions](#).

Parameter No.

A Send Sequence can contain any number of wildcards. Each set of consecutive wildcards is considered a separate parameter. The value for each parameter is entered separately.

Minimum Characters Required

For each '?' wildcard exactly one character is required. Therefore, the minimum number of characters required is equal to the number of '?' wildcards within one parameter.

NOTE: While the Send Sequence Parameter dialog is shown, all serial communication is paused. Docklight does not receive any data and does not send any (periodical) Send Sequences.

8.7 Dialog: Project Settings - Communication

Menu Tools >  Project Settings... | Communication

Communication Mode

Send/Receive

Docklight acts both as transmitter and receiver of serial data. This mode is used when [Testing the functionality or the protocol implementation of a serial device](#) or [simulating a serial device](#).

Naming conventions: The received data (RX) will be displayed and processed as "Channel 1", the transmitted data (TX) will be displayed as "Channel 2".

Monitoring

Docklight receives serial data on two different communication channels. This mode is used, for example, when [Monitoring the communication between two devices](#).

Naming conventions: The serial data from device 1 is "Channel 1", the data from device 2 is "Channel 2".

Communication Channels - Serial COM ports or Docklight TAP ports

Choose one (or in Monitoring Mode: two) COM ports from the dropdown list. The dropdown list shows all COM ports available on your PC via the *Windows* operating system. You can also type in any COM port from COM1 to COM256 manually.

For [Docklight Tap](#) monitoring applications, open the dropdown list and choose the TAP port (e.g. TAP0 for Channel 1, and TAP1 for Channel 2) from the 'USB Tap' section below the COM ports. The TAP connections are only available if Communication Mode is set to 'Monitoring', the Docklight Tap is plugged in and the Docklight Tap USB device drivers are installed properly.

COM Port Settings

Baud Rate

Choose a standard baud rate from the dropdown list, or use a non-standard baud rate by typing any integer number between 110 and 9999999.

NOTE: Non-standard baud rates may not work correctly on all COM ports, dependant on the capabilities of your COM port's hardware UART chip. You will receive no warning, if any non-standard rate cannot be applied.

NOTE: Although Docklight's Project Settings allow you to specify baud rates up to 9 MBaud, this

does not mean Docklight is able to handle this level of throughput continuously. The average data throughput depends very much on your PC's performance and the Docklight display settings. See also [How to Increase the Processing Speed](#).

Data Bits and Stop Bits

Specify the number of data bits and stop bits here. As with the baud rate, some of the available settings may not be supported by the COM port device(s) on your PC.

Parity

All common parity check options are available here. (The settings 'Mark' and 'Space' will probably not be used in practical applications. 'Mark' specifies that the parity bit always is 1, 'Space' that the parity bit is always 0, regardless of the character transmitted.)

Parity Error Character

This is the character that replaces an invalid character in the data stream whenever a parity error occurs. You should specify an ASCII character (printing or non-printing) that does not usually appear within your serial data stream. Characters may be defined by entering the character itself or entering its decimal ASCII code (please enter at least two digits).

NOTE: Choose "(ignore)" for the Parity Error Character if you need to transmit/receive the parity bit but Docklight should preserve all incoming characters, even when the parity bit is wrong. This is useful for applications where a 9th bit is used for addressing purposes and not for error checking.

8.8 Dialog: Project Settings - Flow Control

Menu Tools > Project Settings... | Flow Control

Used to specify additional hardware or software flow control settings for serial communications in Docklight [Send/Receive Mode](#).

Flow Control Support

Off

No hardware or software [flow control](#) mechanism is used. RTS and DTR are enabled when the COM port is opened.

Manual

Use this mode to control the RTS and DTR signals manually and display the current state of the CTS, DSR, DCD and RI lines. If flow control is set to "Manual", an additional status element is displayed in the Docklight main window. You may toggle the RTS and DTR lines by double clicking on the corresponding indicator.

NOTE: Flow control signals are not treated as communication data and will not be displayed in the communication window or logged to a file.

Hardware Handshaking, Software Handshaking

Support for RTS/CTS hardware flow control and XON/XOFF software flow control. These are expert settings rarely required for recent communication applications.

RS485 Transceiver Control

Some RS232-to-RS485 converters require manual RTS control, i.e. the RS232 device (PC) tells the converter when it should enable its RS485 driver for transmission. If you choose "RS485 Transceiver Control", the COM port sets RTS to High before transmitting the first character of a [Send Sequence](#), and resets it to Low after the last character has been transmitted.

NOTE: Many USB-to-Serial converters or virtual COM port drivers do not implement the *Windows* RTS_CONTROL_TOGGLE mode properly. If you experience problems with RS485 Transceiver Control, try using a PC with an on-board COM interface or a standard PCI COM card.

8.9 Dialog: Project Settings - Communication Filter

Menu Tools >  Project Settings... | Communication Filter

Use the **Contents Filter** option if you do not need to see the original communication data on the serial line and only require the additional comments inserted by a Receive Sequence. This is useful for applications with high data throughput, where most of the data is irrelevant for testing and you only need to watch for very specific events. These events (and related display output) can be defined using [Receive Sequences](#).

8.10 Dialog: Options

Menu Tools >  Options...

Display

Formatted Text Output (Rich Text Format)

used for setting the appearance of the Docklight communication window. The two different serial data streams, "Channel 1" and "Channel 2", may be displayed using different colors and styles. The standard setting uses different colors for the two channels, but using different font styles (e.g. Italics for "Channel 2") is also possible. You may also choose the overall font size here.

NOTE: If you change the font size, the communication window contents will be deleted. For all other changes, Docklight will try to preserve the display contents.

Plain Text Output (faster display, but no colors & fonts)

The formatted text output is similar to a word processor and consumes a considerable amount of CPU time. It also requires frequent memory allocation and deallocation which might decrease your PC performance. So if you are monitoring a high-speed communication link, but still want to keep an eye on the serial data transferred, try using the "Plain Text Output" format.

Control Characters (ASCII 0 - 31)

For communication data containing both printing ASCII text as well as non-printing control characters, it is sometimes helpful to see the names of the occurring control characters in the ASCII mode display window. Docklight provides an optional display settings to allow this. You can also suppress the control characters (except CR and LF) for cases when this would clutter your display.

Display Modes

Communication Window Modes

By default, Docklight will display four representations of the serial data streams: ASCII, HEX, Decimal and Binary. You may deactivate some of these modes to increase Docklight's overall performance. For example, the Binary representation of the data is rarely required. Disabling Binary mode for the communication window will considerably increase processing speed. Even when turned off for the communication window, logging in all formats is still possible.

See also the **Plain Text Output** option above.

Date/Time Stamps

Adding a Date/Time Stamp

Docklight adds a date/time stamp to all data that is transmitted or received. You may choose to insert this date/time stamp into the communication window and the log file whenever the data flow direction changes between Channel 1 and Channel 2.

For applications where the data flow direction does not change very often, you may want to have additional date/time stamps at regular time intervals. For this, activate the **Clock - additional date/time stamp...** option then and choose a time interval.

On a half duplex line (e.g. 2 wire RS485), changes in data direction are difficult to detect. Still, in most applications there will be a pause on the communication bus before a new device starts sending. Use the **Pause detection...** option to introduce additional time stamps and make the pauses visible in your communication log.

Date/Time Format

Docklight offers time stamps with a resolution of up to 1/1000 seconds (1 millisecond). For compatibility to earlier Docklight versions (V1.8 and smaller), 1/100 seconds is available, too.

NOTE: The resulting time tagging accuracy can be considerably different, e.g. 10-20 milliseconds only. The actual accuracy depends on your serial communications equipment, your PC configuration, the Docklight Display Settings (see above) and the Docklight [Expert Options](#). See the section [How to Obtain Best Timing Accuracy](#) for details.

Control Characters Shortcuts

Here you can define your own keyboard shortcuts for ASCII Control Characters (ASCII code < 32), or for any character code > 126. Keyboard shortcuts can be used within the following Docklight dialogs and functions

- [Dialog: Edit Send Sequence](#)
- [Dialog: Edit Receive Sequence](#)
- [Dialog: Find Sequence](#)
- [Dialog: Send Sequence Parameter](#)
- [Keyboard Console](#)

For each character from decimal code 0 to 31 and from 127 to 255, you can define a keyboard combination to insert this character into a sequence (**Shortcut**). You may also define a letter which is used to display this control character when editing a sequence in ASCII mode (**Editor**).

Double click to change the value of a **Shortcut** or **Editor** field.

Predefined shortcuts are:

Ctrl+Enter for carriage return / <CR> / decimal code 13

Ctrl+Shift+Enter for line feed / <LF> / decimal code 10

8.11 Dialog: Customize HTML Output

This dialog allows you to change the appearance of the HTML log files, by modifying the HTML template code that Docklight uses when generating the HTML log file data.

You need some basic understanding of HTML documents and CSS style attributes. We recommend <http://www.htmldog.com> (English) or <http://www.selfhtml.org> (German and French) for a quick overview on these topics.

HTML Header Template

The HTML document header. Here you can change the font applied to the log file data, using the following CSS style attributes:

CSS Style Attribute	Description and Example
font-family	Defines one or several fonts (or: font categories) that the HTML browser should use to print a text. If the browser does not support

	<p>the first font, it will try the second one, a.s.o. The last font usually defines a generic font category that every browser supports.</p> <p>Examples:</p> <pre>font-family:'Courier New', Courier, monospace font-family:'Times New Roman', Times, serif font-family:arial, helvetica, sans-serif</pre>
font-size	<p>Specifies the font size. Both, absolute and relative sizes are possible. Examples for absolute font sizes:</p> <pre>font-size:12pt font-size:xx-small font-size:x-small font-size:small font-size:medium font-size:large font-size:x-large font-size:xx-large</pre> <p>Examples for relative font sizes (relative to the parent HTML element)</p> <pre>font-size:smaller font-size:larger font-size:90%</pre>

NOTE: Use the semicolon (";") as a separator between two different CSS style attributes, e.g.
`font-family:sans-serif; font-size:small`

NOTE: Docklight will insert additional <u> (underline), <i> (italic) and (bold) HTML tags, if such formatting options are activated in the [Display Settings](#). You do not have to use the **font-style** or **font-weight** attribute to create these effects.

HTML Footer Template

Adds additional footer text and closes the HTML document.

Data Element Template

For every new piece of log file information (channel 1 data, channel 2 data, or a comment text), a new tag with different text color is added to the HTML log file.

The template code for the header, footer and data parts contains Docklight-specific wildcards which must not be deleted:

Wildcard	Description
%BACKCOLOR%	The background color, as selected in the Display Settings
%HEADERMSG%	Header text at the start of the log file
%FOOTERMSG%	Footer text at the end of the log file
%DATA%	a chunk of the log file data: channel 1 data, channel 2 data, or a comment text
%TEXTCOLOR%	The text color to apply for %DATA%, as selected in the Display Settings

When generating a log file, Docklight replaces the wildcards with the current display settings and the actual communication data.

8.12 Dialog: Expert Options

Menu Tools > Expert Options...


Expert Options are additional settings for specialized applications with additional requirements (e.g. high time tagging accuracy).

Performance

Communication Driver Mode

Use **External / High Priority Process** mode to work around a common problem for any Windows user mode application: unspecified delays and timing inaccuracies can be introduced by the Windows task/process scheduling, especially if you are running other applications besides Docklight. **External / High Priority Process** mode is recommended for high accuracy / low latency monitoring using the [Docklight Tap](#).

In **External / High Priority Process** mode, the data collection in Docklight becomes a separate Windows process with realtime priority class. It will be executed with higher priority than any other user application or additional application software like Antivirus. For best results you need to be logged in as an **Administrator**. Otherwise the data collection process will run with the maximum permitted priority, but not "realtime class".

NOTE: **External / High Priority Process** mode must be used with care, especially when you intend to monitor a high-speed data connection with large amounts of data. The PC might become unresponsive to user input. To resolve such a situation, simply "pull the plug": First disconnect the data connections or the monitoring cable to bring down the CPU load and restore the responsiveness. Then choose  **Stop communication** in Docklight.

NOTE: See the section [How to Obtain Best Timing Accuracy](#) for some background information on timing accuracy.


Docklight Monitoring Mode

When [Monitoring Serial Communications Between Two Devices](#), all received data from one COM port is re-sent on the TX channel of the opposite COM port by default ("Data Forwarding"). This is intended for special applications that require routing the serial data traffic through Docklight using standard RS232 cabling.

Use the **No Data Forwarding** Expert Option for applications with two serial COM ports where you need to avoid that any TX data is sent. This can be used to improve performance when using a [Docklight Monitoring Cable](#), or to work around problems caused with instable serial device drivers.

For [Docklight Tap](#) applications (e.g. using Communication Channel TAP0 / TAP1), the 'Data Forwarding' setting has no effect. The Docklight Tap is accessed in read-only mode always, and no data is forwarded.

8.13 Keyboard Console

The Keyboard Console tool allows you to send keyboard input directly to the serial port. It can be activated using the menu **Tools >  Keyboard Console On**. The keyboard console is only available for [communication mode Send/Receive](#).

After activating the keyboard console, click in the [communication window](#) and type some characters.

Docklight will transmit the characters directly through the selected serial port. The communication window will display the characters the same way it does a [Send Sequence](#).

NOTE: The Keyboard Console tool supports pasting and transmitting a [character sequence](#) from the clipboard, using **Ctrl + V**. This is similar to pasting clipboard data inside the [Edit Send Sequence Dialog](#). Clipboard contents that exceeds the maximum sequence size of 1024 characters gets truncated.

NOTE: The keyboard console is not a full-featured terminal and does not support specific terminal

standards, such as VT 100. The Enter key is transmitted as <CR> (ASCII 13) plus <LF> (ASCII 10), as per the *Windows* standard text file format. Use [control character shortcuts](#) to send other ASCII control characters.

9 Support

9.1 Web Support and Troubleshooting

For up-to-date FAQs and troubleshooting information, see our online support pages available at

http://www.docklight.de/support_en.htm

9.2 E-Mail Support

We provide individual e-mail support to our registered customers. Please include your Docklight license key number in your request. We will contact you as soon as possible to find a solution to your problem. Send your support request to

docklight@fuh-edv.de

10 Appendix

10.1 ASCII Character Set Tables

Control Characters

Dec	Hex	ASCII Char.	Meaning
0	00	NUL	Null
1	01	SOH	Start of heading
2	02	STX	Start of text
3	03	ETX	Break/end of text
4	04	EOT	End of transmission
5	05	ENQ	Enquiry
6	06	ACK	Positive acknowledgment
7	07	BEL	Bell
8	08	BS	Backspace
9	09	HT	Horizontal tab
10	0A	LF	Line feed
11	0B	VT	Vertical tab
12	0C	FF	Form feed
13	0D	CR	Carriage return
14	0E	SO	Shift out
15	0F	SI	Shift in/XON (resume output)
16	10	DLE	Data link escape
17	11	DC1	XON - Device control character 1
18	12	DC2	Device control character 2
19	13	DC3	XOFF - Device control character 3
20	14	DC4	Device control character 4
21	15	NAK	Negative Acknowledgment
22	16	SYN	Synchronous idle
23	17	ETB	End of transmission block
24	18	CAN	Cancel
25	19	EM	End of medium
26	1A	SUB	substitute/end of file
27	1B	ESC	Escape
28	1C	FS	File separator
29	1D	GS	Group separator
30	1E	RS	Record separator
31	1F	US	Unit separator

Printing Characters

Dec	Hex	ASCII Char.	Meaning
32	20		Space
33	21	!	!
34	22	"	"
35	23	#	#
36	24	\$	\$
37	25	%	%
38	26	&	&
39	27	'	'
40	28	((
41	29))
42	2A	*	*
43	2B	+	+
44	2C	,	,
45	2D	-	-
46	2E	.	.
47	2F	/	/

48	30	0	Zero
49	31	1	One
50	32	2	Two
51	33	3	Three
52	34	4	Four
53	35	5	Five
54	36	6	Six
55	37	7	Seven
56	38	8	Eight
57	39	9	Nine
58	3A	:	:
59	3B	;	;
60	3C	<	<
61	3D	=	=
62	3E	>	>
63	3F	?	?
64	40	@	@
65	41	A	A
66	42	B	B
67	43	C	C
68	44	D	D
69	45	E	E
70	46	F	F
71	47	G	G
72	48	H	H
73	49	I	I
74	4A	J	J
75	4B	K	K
76	4C	L	L
77	4D	M	M
78	4E	N	N
79	4F	O	O
80	50	P	P
81	51	Q	Q
82	52	R	R
83	53	S	S
84	54	T	T
85	55	U	U
86	56	V	V
87	57	W	W
88	58	X	X
89	59	Y	Y
90	5A	Z	Z
91	5B	[[
92	5C	\	\
93	5D]]
94	5E	^	^
95	5F	~	~
96	60		
97	61	a	a
98	62	b	b
99	63	c	c
100	64	d	d
101	65	e	e
102	66	f	f
103	67	g	g
104	68	h	h
105	69	i	i
106	6A	j	j
107	6B	k	k
108	6C	l	l
109	6D	m	m
110	6E	n	n
111	6F	o	o

112	70	p	p
113	71	q	q
114	72	r	r
115	73	s	s
116	74	t	t
117	75	u	u
118	76	v	v
119	77	w	w
120	78	x	x
121	79	y	y
122	7A	z	z
123	7B	{	{
124	7C		
125	7D	}	}
126	7E	~	Tilde
127	7F	DEL	Delete

10.2 Hot Keys

General Hot Keys

Applies to

- Communication window (ASCII, HEX, Decimal, Binary)
- Edit Send Sequence dialog / Edit Receive Sequence dialog
- Docklight Notepad

Function	Hot Key
Context-specific help	F1
Cut	Ctrl+X
Copy	Ctrl+C
Paste	Ctrl+V
Delete	Del
Select all	Ctrl+A

Context-specific Hot Keys

Docklight menu

Menu	Function	Hot Key
File	New Project	Ctrl+N
File	Open Project	Ctrl+O
File	Save Project	Ctrl+S
Edit	Find Sequence in Comm.Window	Ctrl+F
Run	Start Communication	F5
Run	Stop Communication	F6
Tools	Keyboard Console On	Ctrl+F5
Tools	Keyboard Console Off	Ctrl+F6
Tools	Show / Hide Docklight Notepad	F12

Communication Window

Function	Hot Key
----------	---------

Find a Sequence	Ctrl+F
Clear All Communication Windows	Ctrl+W
Toggle Between ASCII, HEX, Decimal and Binary Representation	Ctrl+Tab

Send Sequences / Receive Sequences List

Function	Hot Key
Delete This Sequence	Del
Edit This Sequence	Ctrl+E
Send This Sequence - <i>Send Sequences List only</i> -	Space

Edit Send Sequence Dialog / Edit Receive Sequence Dialog

Function	Hot Key
Cancel	Esc
Wildcard '?' (matches one character)	F7
Wildcard '#' (matches one or zero characters)	F8

Notepad Window

Function	Hot Key
Default Font	Ctrl+D

10.3 RS232 Connectors / Pinout


The most common connectors for RS232 communication are

- 9-pole SUB D9 (EIA/TIA 574 standard). Introduced by IBM and widely used. See below.
- [25-pole SUB D25](#) (RS232-C). This is the original connector introduced for the RS232 standard. It provides a secondary communication channel.
- [8-pole RJ45](#) (RS232-D, according to EIA/TIA-561 standard).

RS232 SUB D9 Pinout

View: Looking into the male connector.

Pinout: From a [DTE](#) perspective (the [DTE](#) transmits data on the TX Transmit Data line, while the [DCE](#) receives data on this line)




Pin No.	Signal Name	Description	DTE in/out
1	DCD	Data Carrier Detect	Input
2	RX	Receive Data	Input
3	TX	Transmit Data	Output

4	DTR	Data Terminal Ready	Output
5	SGND	Signal Ground	-
6	DSR	Data Set Ready	Input
7	RTS	Request To Send	Output
8	CTS	Clear To Send	Input
9	RI	Ring Indicator	Input


RS232 SUB D25 Pinout

View: [DTE](#) perspective, looking into the male connector



Pin No.	Signal Name	Description
1	-	Protective/Shielding Ground
2	TX	Transmit Data
3	RX	Receive Data
4	RTS	Request To Send
5	CTS	Clear To Send
6	DSR	Data Set Ready
7	SGND	Signal Ground
8	DCD	Data Carrier Detect
9	-	Reserved
10	-	Reserved
11	-	Unassigned
12	SDCD	Secondary Data Carrier Detect
13	SCTS	Secondary Clear To Send
14	STx	Secondary Transmit Data
15	TxCLK	Transmit Clock
16	SRx	Secondary Receive Data
17	RxCLK	Receive Clock
18	LL	Local Loopback
19	SRTS	Secondary Request To Send
20	DTR	Data Terminal Ready
21	RL/SQ	Remote Loopback / Signal Qualify Detector
22	RI	Ring Indicator
23	CH/CI	Signal Rate Selector
24	ACLK	Auxiliary Clock
25	-	Unassigned

RS232-D, RJ45 pinout



Pin No.	Signal Name	Description
1	DSR / RI	Data Set Ready / Ring Indicator
2	DCD	Data Carrier Detect
3	DTR	Data Terminal Ready
4	SGND	Signal Ground
5	RX	Receive Data
6	TX	Transmit Data
7	CTS	Clear To Send
8	RTS	Request To Send

10.4 Standard RS232 Cables

RS232 Connections


When connecting two serial devices, different cable types must be used, depending on the characteristics of the serial device and the type of communication used.

Overview of RS232 SUB D9 interconnections

serial device 1	serial device 2	flow control (handshaking)	recommended cable
DTE (Data Terminal Equipment)	DTE	no handshake signals	simple null modem cable
DTE	DTE	DTE/DCE compatible hardware flow control	null modem cable with partial handshaking
DTE	DCE (Data Communications Equipment)	no handshake signals	simple straight cable
DTE	DCE	hardware flow control	full straight cable
DCE	DCE	no handshake signals	simple null modem cable, but with SUB D9 male connectors on both ends
DCE	DCE	hardware flow control	null modem cable with partial handshaking but with SUB D9 male connectors on both ends


SUB D9 Simple Straight Cable

Area of Application: [DTE-DCE](#) Communication where no additional handshake signals are used.




SUB D9 Full Straight Cable

Area of Application: [DTE-DCE](#) Communication with hardware flow control using additional handshake signals.




SUB D9 Simple Null Modem Cable without Handshaking

Area of Application: [DTE-DTE](#) Communication where no additional handshake signals are used.



SUB D9 Null Modem Cable with Partial Handshaking

Area of Application: [DTE-DTE](#) Communication with DTE/DCE compatible hardware flow control. Works also when no handshake signals are used.




10.5 Docklight Monitoring Cable RS232 SUB D9

Docklight Monitoring Mode requires a full-duplex monitoring cable that feeds the two data directions into two separate COM ports.

Area of application: [Monitoring serial communications between two devices](#)

We offer a custom RS232 cable that is designed for the use with Docklight Monitoring Mode, according to the cable specification below. Visit our [product overview](#) pages for the [Docklight Monitoring Cable](#), a professional and rugged cable solution for industrial applications.



10.6 Docklight Tap

Docklight Tap is a full-duplex RS232 communications monitoring solution for the USB port.

Area of Application: [Monitoring serial communications between two devices](#)



Docklight has built-in support for the Docklight Tap. It recognizes the dual port USB serial converter and offers high-speed, low-latency access to the monitoring data using the Receive Channel syntax TAP0, TAP1, ... (see the [Docklight Project Settings](#) and [How to Obtain Best](#)

[Timing Accuracy](#) for details).

Please see our [product overview](#) pages for more information about the Docklight Tap.



Device 1

Sub D9
female



Device 2

Sub D9
male



11 Glossary / Terms Used

11.1 Action

For a Receive Sequence, the user may define an action that is performed after receiving the specified sequence. Possible actions are

- Sending a [Send Sequence](#)
Only Send Sequences without any wildcards can be used
- Inserting a comment
A user-defined text or an additional date/time stamp is added to the communication data window and log file
- Triggering a [Snapshot](#)
- Stopping communication

11.2 Break

A break state on an [RS232](#) connection is characterized by the TX line going to Space (logical 0) for a longer period than the maximum character frame length including start and stop bits. Some application protocols, e.g. [LIN](#), use this for synchronization purposes.

11.3 CAN

Controller Area Network. A serial bus communication standard originally developed for automotive applications, but now widely used in many kinds of distributed embedded systems. See also <http://www.can-cia.org>

11.4 Character

A character is the basic unit of information processed by Docklight. Docklight always uses 8 bit characters. Nevertheless, the communication settings also allow data transmission with 7 bits or less. In this case, only a subset of the 256 possible 8 bit characters will be used but the characters will still be stored and processed using an 8 bit format.

11.5 CRC

Cyclic Redundancy Code. A CRC is a method to detect whether a received sequence/message has been corrupted, e.g. by transmission errors. This is done by constructing an additional checksum value that is a function of the message data, and then appending this value to the original message. The receiver calculates the checksum from the received data and compares it to the transmitted CRC value to see if the message is unmodified. CRCs are commonly used because they allow the detection of typical transmission errors (bit errors, burst errors) with a very high accuracy.

CRC algorithms are based on polynomial arithmetic, and come in many different versions. Common algorithms are CRC-CCITT, CRC-16 and CRC-32. An example of an application protocol that uses a CRC is [MODBUS over Serial Line](#).

A very popular article about CRCs is "Easier said than done (Michael Barr) - A guide to CRC calculation": <http://www.netrino.com/Connecting/2000-01/>

Docklight Scripting's CRC functionality (DL.CalcChecksum) was inspired by the above article and the proposed Boost CRC library:

<http://www.boost.org/libs/crc/index.html>

Last not least, if you are truly fascinated by CRC alchemy, you will, sooner or later, run into the following article:

"A Painless Guide to CRC Error Detection Algorithms" by Ross N. Williams

<http://www.ross.net/crc/>

11.6 DCE

Data Communications Equipment. The terms DCE and DTE refer to the serial devices on each side of an RS232 link. A modem is a typical example of a DCE device. DCE are normally equipped with a **female SUB D9** or SUB D25 connector. See also [DTE](#).

11.7 DTE

Data Terminal Equipment. The terms DCE and DTE refer to the serial devices on each side of an RS232 link. A PC or a terminal are examples of a typical DTE device. DTE are commonly equipped with a **male SUB D9** or SUB D25 connector. All [pinout specifications](#) are written from a DTE perspective. See also [DCE](#).

11.8 Flow Control

Flow control provides a mechanism for suspending transmission while one device is busy or for some reason cannot further communicate. The [DTE](#) and [DCE](#) must agree on the flow control mechanism used for a communication session. There are two types of flow control: hardware and software.

Hardware Flow Control

Uses voltage signals on the RS232 status lines RTS / DTR (set by [DTE](#)) and CTS / DSR (set by [DCE](#)) to control the transmission and reception of data. See also [RS232 pinout](#).

Software Flow Control

Uses dedicated ASCII control characters (XON / XOFF) to control data transmission. Software flow control requires text-based communication data or other data that does not contain any XON or XOFF characters.

11.9 LIN

Local Interconnect Network. A low cost serial communication bus targeted at distributed electronic systems in vehicles, especially simple components like door motors, steering wheel controls, climate sensors, etc. See also <http://www.lin-subbus.org>

11.10 MODBUS

MODBUS is an application layer messaging protocol that provides client/server communications between devices connected on different types of buses or networks. It is commonly used as "MODBUS over Serial Line" in RS422/485 networks, but can be implemented using TCP over Ethernet as well ("MODBUS TCP").

Two different serial transmission modes for MODBUS are defined: "RTU mode" for 8 bit binary transmissions, and "ASCII mode". "RTU mode" is the default mode that must be implemented by all devices.

See <http://www.modbus.org> for a complete specification of the MODBUS protocol.

11.11 Receive Sequence

A Receive Sequence is a [sequence](#) that can be detected by Docklight within the incoming serial data. A Receive Sequence is specified by

1. an unique name (e.g. "Modem Answer OK"),
2. a character sequence (e.g. "6F 6B 13 10" in HEX format),
3. an [action](#) that is triggered when Docklight receives the defined sequence.

11.12 RS232

The RS232 standard is defined by the EIA/TIA (Electronic Industries Alliance / Telecommunications Industry Associations). The standard defines an asynchronous serial data transfer mechanism, as well as the physical and electrical characteristics of the interface.

RS232 uses serial bit streams transmitted at a predefined baud rate. The information is separated into characters of 5 to 8 bits lengths. Additional start and stop bits are used for synchronization, and a parity bit may be included to provide a simple error detection mechanism.

The electrical interface includes unbalanced line drivers, i.e. all signals are represented by a voltage with reference to a common signal ground. RS232 defines two states for the data signals: mark state (or logical 1) and space state (or logical 0). The range of voltages for representing these states is specified as follows:

Signal State	Transmitter Voltage Range	Receiver Voltage Range
Mark (logical 1)	-15V to -5V	-25V to -3V
Space (logical 0)	+5V to +15V	+3V to +25V
Undefined	-5V to +5V	-3V to +3V

The physical characteristics of the RS232 standard are described in the section [RS232 Connectors / Pinout](#)

11.13 RS422

An RS422 communication link is a four-wire link with balanced line drivers. In a balanced differential system, one signal is transmitted using two wires (A and B). The signal state is represented by the voltage across the two wires. Although a common signal ground connection is necessary, it is not used to determine the signal state at the receiver. This results in a high immunity against EMI (electromagnetic interference) and allows cable lengths of over 1000m, depending on the cable type and baud rate.

The EIA Standard RS422-A "Electrical characteristics of balanced voltage digital interface circuits" defines the characteristics of an RS422 interface.

Transmitter and receiver characteristics according to RS422-A are:

Signal State	Transmitter Differential Voltage V_{AB}	Receiver Differential Voltage V_{AB}
Mark (or logical 1)	-6V to -2V	-6V to -200mV
Space (or logical 0)	+2V to +6V	+200mV to 6V
Undefined	-2V to +2V	-200mV to +200mV

Permitted Common Mode Voltage V_{cm} (mean voltage of A and B terminals with reference to signal ground): -7V to +7V

11.14 RS485

The RS485 standard defines a balanced two-wire transmission line, which may be shared as a bus line by up to 32 driver/receiver pairs. Many characteristics of the transmitters and receivers are the same as [RS422](#). The main differences between RS422 and RS485 are

- Two-wire (half duplex) transmission instead of four-wire transmission
- Balanced line drivers with tristate capability. The RS485 line driver has an additional "enable" signal which is used to connect and disconnect the driver to its output terminal. The term "tristate" refers to the three different states possible at the output terminal: mark (logical 1), space (logical 0) or "disconnected"
- Extended Common Mode Voltage (V_{cm}) range from -7V to +12V.

The EIA Standard RS485 "Standard for electrical characteristics of generators and receivers for use in balanced digital multipoint systems" defines the characteristics of an RS485 system.

11.15 Send Sequence

A Send Sequence is a [sequence](#) that can be sent by Docklight. A Send Sequence is specified by

1. an unique name (e.g. "Set modem speaker volume"),
2. a character sequence (e.g. "41 54 4C 0D 0A" in HEX format).

There are two ways to make Docklight send a sequence:

- Sending a sequence can be triggered manually by pressing the send button in the Send Sequences list (see [Main Window](#)).
- Sending a sequence may be one possible reaction when Docklight detects a specific Receive Sequence within the incoming data (see [Action](#)).

11.16 Sequence

A sequence consists of one or more 8 bit [characters](#). A sequence can be any part of the serial communications you are analyzing. It can consist of printable ASCII characters, but may also include every non-printable character between 0 and 255 decimal.

Example:

ATL2 (ASCII format)

41 54 4C 0D 0A (HEX format)

This sequence is a modem command to set the speaker volume on AT compatible modems. It includes a Carriage Return (0D) and a Line Feed (0A) character at the end of the line.

The maximum sequence size in Docklight is 1024 characters.

11.17 Sequence Index

The Sequence Index is the element number of a Send Sequence within the Send Sequence List, or of a Receive Sequence within the Receive Sequence List. The Sequence Index is displayed in the upper left corner of the [Edit Send Sequence](#) or [Edit Receive Sequence](#) dialog.

11.18 Serial Device Server

A Serial Device Server is a network device that offers one or more serial COM ports ([RS232](#), [RS422/485](#)) and transmits/receives the serial data over an Ethernet network. Serial Device Servers are a common way for upgrading existing devices that are controlled via serial port and make them "network-enabled".

11.19 Snapshot

Creating a snapshot in Docklight means generating a display of the serial communication shortly before and after a [Trigger](#) sequence has been detected. This is useful when testing for a rare error which is characterized by a specific sequence. See [Catching a specific sequence and taking a snapshot...](#) for more information.

11.20 Trigger

A Trigger is a [Receive Sequence](#) with the "Trigger" option enabled (see [Dialog: Edit Receive Sequence](#)). When the [Snapshot](#) function is enabled, Docklight will not produce any output until a trigger sequence has been detected in the serial communication data. See [Catching a specific sequence and taking a snapshot...](#) for more information.

11.21 UART

Universal Asynchronous Receiver / Transmitter. The UART is the hardware component that performs the main serial communications tasks:

- converting characters into a serial bit stream
- adding start / stop / parity bits, and checking for parity errors on the receiver side
- all tasks related to timing, baud rates and synchronization

Common UARTs are compatible with the 16550A UART. They include a 16 byte buffer for incoming data (RX FiFo), and a 16 byte buffer for outgoing data (TX FiFo). Usually these buffers can be disabled/enabled using the *Windows Device Manager* and opening the property page for the appropriate COM port (e.g. COM1).

11.22 Virtual Null Modem

A virtual null modem is a PC software driver which emulates two serial COM ports that are connected by a [null modem cable](#). If one PC application sends data on one virtual COM port, a second PC application can receive this data on the second virtual COM port and vice versa.

By using a virtual null modem driver on your PC you can easily debug and simulate serial data connections without the use of real [RS232](#) ports and [cables](#).

Virtual COM connections do not give you the same timing as real RS232 connections and usually do not emulate the actual bit-by-bit transmission using a predefined baud rate. Any data packet sent on the first COM port will appear in the second COM port's receive buffer almost immediately. For most debugging and simulation purposes this limitation can be easily tolerated. Some virtual null modem drivers offer an additional baud rate emulation mode, where the data transfer is delayed to emulate a real RS232 connection and its limited transmission rate.

For an Open Source *Windows* software that has been successfully tested with Docklight, see <http://com0com.sourceforge.net/>

11.23 Wildcard

A wildcard is a special character that serves as a placeholder within a sequence. It may be used for [Receive Sequences](#) when parts of the received data are unspecified, e.g. measurement readings reported by a serial device. Wildcards can also be used to support parameters in a [Send Sequence](#).

Two types of wildcards are available in Docklight:

Wildcard '?' : Matches exactly one arbitrary character (any ASCII code between 0 and 255)

Wildcard '#' : Matches zero or one character. This is useful for supporting variable length command arguments (e.g. a status word) in Send / Receive Sequences. See [Checking for sequences with random characters](#) or [Sending commands with parameters](#) for examples and additional information.